HYPERCOM
PROGRAMMING REQUEST

CROSSCHECK, INC.

Date: **Store Number:**   **Sales Office:**   **State:**

Your Name: **Extension:**   **Dept:**

Store DBA: **Store Ph#:**

Contact Name: **Contact Ph#:**

Terminal Model:

Checkreader/Imager: **Model:**   **Manufacturer:**

Credit Card Processor: **Phone #:**

Credit Card Merchant Number:

Hypercom T7 Terminals	Hypercom ICE 5000/5500/5700 Terminals

From the main screen: (press **CANCEL** to be sure)
- Press **FUNCTION,** then **2,** then **ENTER**
- Enter Password: **0000, ENTER**
   ~ If the above password doesn't work, try again using each of the following until it does: **1111, 1234, 0010, 4194, 5965, 5126, 7867 (TRF Maint password is 166831, second password is 1739)**
- The Screen will display the **Terminal ID**
- **Record the Terminal ID below**
▼ ▼ ▼ ▼ ▼ ▼ ▼
	From the Main Screen: (press **CANCEL** to be sure)
	- Touch the **Top Menu Bar** on the screen.
	On the resulting **Menu Screen**
	- Touch **Set Up** on the screen
	- Touch **Terminal** on the screen
	- Type in the password **0000** then press **<ENTER>**
	   ~ If the above password doesn't work, try again using each of the following until it does: **1111, 1234, 0010, 4194, 5965, 5126, 7867 (TRF Maint password is 166831, second password is 1739)**
	- Touch **ALL** on the screen
	- The terminal will display the **Terminal ID**,
	- **Record the Terminal ID below:**
	▼ ▼ ▼ ▼

Terminal ID#:

From the screen showing the Terminal ID: - Press **ENTER** - **Record the Init Phone# below ►►►** Press **CANCEL** (returns to main screen ▼ ▼	From the screen showing the Terminal ID: - Press **ENTER** - The terminal will show the INIT Phone Number, - **Record the INIT Phone Number below ►►►** Touch the **X** in the upper right corner to return to the main screen. ▼ ▼

Init Phone#:

:: Notes For Tech Support ::

Updated 6/11/07